

## Remote Operations Procedure

This manual describes the procedures for club members to participate in remote operation sessions. These sessions will replace the in-person sessions until COVID restrictions have been lifted and members are comfortable to operate in person.

The concept is that members will act as remote engineers (or conductors) for trains run at members' homes and/or St. Anthony. Trains will start with one host and continue on to the next host. One train will span multiple hosts.

Members will need to familiarize themselves with the track plans to be switched in advance of the operating session. The specific procedures are below.

1. Visit the HOTRAK booking sheet on the club's google drive at <https://docs.google.com/spreadsheets/d/1MhzDLUqY02k1d6Aqc4n7vtTRHMBQIQqzLXNID9dCyks/edit#gid=1907294875>
2. Select the operating session tab at the bottom of the sheet.

The screenshot shows the Google Sheets interface for the 'HOTRAK booking sheet'. The spreadsheet has columns A through E. Column A is labeled 'Date', column B is 'Time', and column C is 'Person'. The data in column A is '31 Dec 2020'. The data in column B includes '9:00', '10:00', '11:00', '13:00', '14:00', and '15:00'. The bottom of the spreadsheet shows a tab for 'Dec 31 2020' and a tab for 'Jan 9/10 2021'. A purple arrow points to the 'Jan 9/10 2021' tab with the text 'Pick operating session tab'.

3. Pick a time slot. Note you are committing for two concurrent sessions, each 40 mins long (max).
4. Go to the [HOTRAK Google calendar](#) and get the remote operating session Zoom invite and IP details.
5. Start to familiarize yourself with the module or layout. Check out track plans on the HOTRAK site at <http://www.hotrak.ca/page4.html> If the actual track work is different you can view it in its panel over the JMRI web server. This will be the case for CAMI.

6. Prior to joining the Zoom meeting, get yourself set up on a computer, laptop or tablet/phone. It is recommended that you view video on the largest screen you have and control the train from a phone or tablet using Withrottle or Engine Driver apps. If you don't have these, you can control the train from the JMRI web throttle. To set yourself up, you need to enter the web server IP address of the host. You can get this address from Zoom invite on the Google calendar from step 4 above.
7. You need to enter this IP address into your browser and throttle app. You will need to open three browser windows set to this IP address. In one window you will navigate to the web throttle (if not using an app), the second window will be set to the switch list and the third will have the panel of the industry you are switching.

When you first enter the IP you will see this screen, focus on the red boxes:

Prairie Pacific Railroad Panels Roster Operations Tables Preferences Help

# Prairie Pacific Railroad

Welcome to *Prairie Pacific Railroad*, powered by [JMRI](#).

### Throttles


[webThrottle](#)  
*webThrottle* provides integrated support for controlling trains, layout elements, and panels from a web browser.  
[Open Now »](#) [Learn More »](#)


[Engine Driver](#)  
*Engine Driver* is a native throttle for Android-powered phones and tablets.  
[Learn More »](#)

[WiThrottle](#)  
*WiThrottle* is a native throttle for the iPhone, iPad, and iPod.  
[Learn More »](#)

[DigiTrainsPro](#)  
*DigiTrainsPro* is a versatile and user friendly model railroad control app. For Android, iOS, and Windows 10.  
[Learn More »](#)

### Open Windows

[Annacis](#)  


[CAMI Block](#)  


### Utilities

**JSON Console**  
 The JSON Console is disabled. ✕  
 A console for directly issuing JSON commands to JMRI.

**Simple Console**  
 The Simple Console is disabled. ✕  
 A console for issuing plain text commands to JMRI.

















**File Access**  
 Directly access certain files and directories:  
[/prefs](#)  
 The preferences directory for the current JMRI profile.  
[/dist](#)  
 The JMRI application installation directory.  
[/web](#)



8. If not using a throttle app, select web throttle. You will see this screen.



o single A A ?


R. Groups / Panels	Turnouts	Routes
 1115 (1115) GM (1115) Athearn Genesis (MP15AC) [Mar...]	 1403 (1403) CP (1403) Athearn Genesis (MP15AC) [Mar...]	 1415 (1415) CP (1415) Athearn Genesis (MP15AC) [Mar...]
 1422 (1422) CP (1422) Athearn Genesis (MP15AC) [Mar...]	 1428 (1428) CP (1428) Athearn Genesis (MP15AC) [Mar...]	 1446 (1446) CP (1446) Athearn Genesis (MP15AC) [Mar...]
 3045 (3045) CN (3045) Scale Trains (GE Tier 4 GEVO) [...]	 4626 (4626) BC Rail (4626) Rapido (Dash 8-40CM) [Mark M]	 6435 (6435) VIA (6435) Rapido (F40PH-2D) [Mark M]
 8334 (8334) UP (8334) Athearn Genesis (SD70ACe) [Ma...]	 8530 (8530) CP (8530) Athearn Ready To Roll (AC4400)...	 8711 (8748) CP (8711) Athearn Genesis (ES44AC) [Mar...]
 8731 (8711) CP (8731) Intermountain (ES44AC) [Mark M]	 8738 (8738) CP (8738) Athearn Genesis (ES44AC) [Mar...]	 8748 (8731) CP (8748) Intermountain (ES44AC) [Mark M]
 9131 (9131) BNSF (9131) Athearn Genesis (SD70M-2) [Ma...]		

You will be using loco 8530, so click on it to get to its web throttle per below.

o STOP A A ?

8530 (8530)


Headlight	Bell	Horn Long	Horn Short	Dim	Mute
-----------	------	-----------	------------	-----	------




▼
▲

The functions are labelled so just click as needed. Direction is controlled by clicking the green up arrow for forward or the red down arrow for reverse. Speed is controlled by clicking in the black box above the arrows. You web throttle is ready.

9. Open up a new browser window (not tab) with the web server IP. From the home screen, click on the CAMI (or whatever layout diagram you need - if available) panel from the middle column. You will then get a dedicated view of the module.
10. Open up a new browser window (not tab). From the home screen, click on Operations in the top menu. From the dropdown select trains. This capability may not be active initially. If not available, skip.



You will then see the train ready for you.



From the CAMI local dropdown, select Conductor.

You will then see what needs to be done at CAMI. The picture below is just an example, you will be switching 3 cars.



## CAMI Local (Yard-CAMI-Yard 3 cars) Conductor

**CAMI** Next Location: City Yard

Scheduled work at CAMI


Train departs CAMI East with 1 cars, 54 feet, 29 tons

### Pick up

CGTX 30748 Tank Oil 50 Black E from Track 9 POL

Move to City Yard

11. Now you are ready to join the Zoom call. In a new browser window join Zoom using the details from step 4. Now rearrange all your browser windows like below. You now have everything you need to run a train.



12. If you are using a throttle app on your phone (Withrottle or Engine Driver) you need to go into settings and enter the throttle server IP address. This IP address is different than what you set up your web browsers with. Note: you can display panel info directly in the app if you don't want to have a separate browser window for it. Get this IP address from the Google calendar Zoom invite (step 4).

13. Once in the Zoom call, the Traffic Supervisor will help you out and direct you to the appropriate Zoom break out room.
14. In the break out room, the host will act as conductor and will coordinate the conduct of the session with you. When ready, operate your throttle normally.
15. When you complete the run, release your train from your throttle. The host will direct you back to the Traffic Supervisor who will direct you to the next host's break out room. Continue to operate the train.
16. When complete, release your train from your throttle, close out your browsers and leave the Zoom call.